

Xpediter Patrol C/S 8.3 Install Instructions

Contents

- Server/Standalone Installation
- Client Installation
- Firewall Configuration

Notes for a successful install

- Login as an administrator account in Windows.
- If upgrading, make sure you are currently running Xpediter version 7.7 or later.
- Include the xpediter.lic file in the same directory as the installer to automatically register Xpediter.

Server/Standalone Installation

- (1) Run Install83.exe, click Next button.
- (2) Choose Server/Standalone type of install, click Next button.
- (3) Choose a location to install (default path recommended), click Next button.
- (4) Choose 3rd-Party drivers needed. Click Install button.
- (5) Note: Most installations will not require these drivers.
- (6) Data Direct ODBC Driver Installation (if required).
- (7) (a) Click Next button.
- (8) (b) Click Yes button.
- (9) (c) Click Next button.
- (10) (d) Click Next button.
- (11) (e) Click Finish button.
- (12) If you are updating a previous installation, the Xpediter Database Maintenance will run.
- (13) If the Xpediter license file was not in the same directory as the installer, then you will need to register Xpediter manually. Enter the Xpediter registration information in the following window. Click OK button when complete.
- (14) Click OK if successful.
- (15) ODBC Driver configuration. If the DataDirect ODBC driver was installed, configure the path to the database. Click OK when complete.
- (16) On a Server/Standalone installation, no Interbase Server configuration should be needed.
- (17) Close the Interbase Server Selection window.
- (18) Borland Database Engine driver installation (if required).
- (19) (a) Click Next button.
- (20) (b) Click Next button.
- (21) (c) Click Next button.
- (22) (d) Click Next button.
- (23) (e) Click Finish button.
- (24) Interbase Registration, enter the provided Interbase certificate ID and key. Click Next.
- (25) Click Finish button.

Client Installation

- (1) Run Install83.exe, click Next button.
- (2) Choose Client type of install, click Next button.
- (3) Choose a location to install (default path recommended), click Install button.
- (4) Interbase Server Selection
- (5) (a) Enter name or IP address of Server.
- (6) (b) Change path to database if applicable and set a unique machine id for the machine you will be installing to. (Can be any number between -99 and 99 just make sure each computer is assigned a different number).
- (7) (c) Click Validate button to check information.
- (8) (d) Click Save button if validation was successful.
- (9) (e) Click X in upper right corner to close window.
- (10) Click Finish button.

Firewall Configuration

Note: An exception is needed for the Interbase Server in order to allow clients to connect to the host database.

- (1) Open the Control Panel in Windows.
- (2) Open System and Security.
- (3) Open Windows Firewall.
- (4) Click Allow a program or feature through Windows Firewall.
- (5) Click Change settings.
- (6) Click Allow another program...
- (7) Click Browse. Choose the ibserver.exe in the bin folder where Borland Database 7.5 Server is installed. Click OK.
- (8) Note: The default location is:
 1. 32-bit Windows: C:\Program Files\Borland\Interbase\bin
 2. 64-bit Windows: C:\Program Files (x86)\Borland\Interbase\bin
- (9) Click Add.
- (10) Click OK.